

DMM B18 V1.0 App

Quick Guide



Address: 125, Mahajan Society, B/H Convent School, Fatehgunj,
Vadodara - 390002, Gujarat, India

Phone: +91 265 2791184 (L), +91 6356615024 (M)

Email: patel.madhukar@gmail.com, innovativeinstrumentsbaroda@gmail.com

Website: www.innovative-instruments.in

GST NO: 24ACQPP6313F1ZK

Contents

1. Software Setup	3
2. Status Window	3
3. Device Port Connection	4
4. Get Measured Data from Meter	4
5. View Recorded Data	5
6. User Profile Setup	7



1. Software Setup Instructions:

1. Install the Software:


- Extract the setup package.
- Double-click the setup file and follow the instructions on the setup window.

2. after Installation:

- The application will be installed in:
C:\Program Files\DMMB18V1App

3. Launch the Application:

- Click the application icon.
- The main window of the application will appear.



2. Status window:




The Purpose of Status window is:-

- To check that device is connected or not connected.
- To track Email sending Progress.

3. Device Port Connection:

Connecting to a Device


1. Click the **“Connect”** button.
2. A window will appear for **port selection**.
3. Select the port where your device is connected.
4. The device will connect automatically once the correct port is selected.



Select device port to Connect.

4. Receiving and Displaying Data:

1. Click the **“Get Data”** button to receive the measured data from the meter.
2. The data will be displayed on the application window automatically.



Users can enter additional details such as **Client Name, Location, Remarks**, etc. These fields are available in the **right-side section** of the application window.

Printing and Sharing Data

Print: Click the **“Print”** button to print the received data. A PDF copy will also be saved at:
C:\Users\{UserName}\Realogview\DMM1.0\Data\PDF


Send: Click the **“Send”** button to share the received data in PDF format.

- Enter the recipient’s **Email Address** before sending.

5. Accessing Past Records :


Click the **“Records”** button.

A new window will appear, allowing you to **view and manage past recorded data**.



- **NOTE:** The Maximum duration is 60 days for Dates selection.

- **Option 1:**



Select first option to get recorded data, between two particular dates.

- **Option 2:**



Select second option to get today's all recorded data.

- **Option 3:**



Select third option to choose file.

- After selecting any record or file, the user can **view or share** the data.
- **Send as Excel:** Share the recorded data in **Excel** format.
- **Send as PDF:** Share the recorded data in **PDF** format.
- **Send File:** Use this option to send a **browsed file**.
- **View Data:** Use this option to display recorded data or a browsed file in **table format**.

- The table will show the data clearly for easy viewing.

Table View

ID	Serial No	MAC Id	Commodity Name	Moisture %	Sample Temperature (°C)	Time	Sample Quantity Req...	Other Information
7	DMMPR67890	DMMPR67890	MAIZE	12.3	29.8	05-08-2023 10:54:14 am	150	
8	DMMPR190623	DMMPR190623	MOONG	11.6	28.5	05-08-2023 10:55:45 am	FULL	
9	TRIAL2301	TRIAL2301	SUNFLOWER	23.1	27.0	05-08-2023 11:09:42 am	150	
10	DMMPR67890	DMMPR67890	MAIZE	12.3	29.8	05-08-2023 11:15:52 am	150	
11	DMMPR67890	DMMPR67890	MAIZE	12.3	29.8	05-08-2023 12:30:12 pm	150	ewrtyujmnhfrhgjds ddfghtfhtgfdsg...
12	DMMPR67890	DMMPR67890	MAIZE	12.3	29.8	05-08-2023 01:36:29 pm	150	
13	DMMBLE15722	DMMBLE15722	TOORDAL	08.2	35.5	05-08-2023 01:57:02 pm	125	
14	TRIAL2301	TRIAL2301	SUNFLOWER	23.1	27.0	06-08-2023 11:31:09 am	150	
15	DMMPR67890	DMMPR67890	MAIZE	12.3	29.8	06-08-2023 11:37:11 am	150	sdfghnm,
16	DMMPR67890	DMMPR67890	MAIZE	12.3	29.8	06-08-2023 01:04:39 pm	150	
17	DMMBLE20721	DMMBLE20721	CHANA DAL	12.3	09.1	07-08-2023 03:14:14 pm	250	qwerthyjhmng vreh vhhvt y54,
18	DMMPR67890	DMMPR67890	MAIZE	12.3	29.8	07-08-2023 03:37:07 pm	150	ergth nfgdgf gsfgstfg,
19	DMMPR190623	DMMPR190623	MOONG	11.6	28.5	07-08-2023 03:46:06 pm	FULL	
20	DMMBLE15722	DMMBLE15722	TOORDAL	08.2	35.5	07-08-2023 03:47:40 pm	125	
21	DMMBLE20721	DMMBLE20721	CHANA DAL	12.3	09.1	07-08-2023 03:49:58 pm	250	
22	TRIAL2301	TRIAL2301	SUNFLOWER	23.1	27.0	07-08-2023 04:01:21 pm	150	

Print Export to pdf Export to Excel

Print: Click “Print” to print the table.


Export as PDF: Click “Export as PDF” to save the table as a PDF.

- The PDF will be stored at:
C:\Users\{UserName}\Realogview\DMM1.0\Records\PDF

Export as Excel: Click “Export as Excel” to save the table as an Excel file.

- The Excel file will be stored at:
C:\Users\{UserName}\Realogview\DMM1.0\Records\Excel

Setup User Profile:



INNOVATIVE INSTRUMENTS Digital Moisture Meter - DMM B18

User Profile :

Connect
Get Data
Records
User Profile
Help
Clients

Status
X
Device is not Connected


Company Name : Innovative Instruments
Email Id : info@innovative-instruments.in
Phone No : 6356615024
Address : No. 125, Mahajan Society, Behind Convent School, Fatehgunj, Vadodara, Gujarat - 390 002, India.

Edit **Save**

Users can enter their personal or company details in this tab.

These details will be included in the **PDF** and **printed copies** for reference, showing who generated the document.

Client's records:



INNOVATIVE INSTRUMENTS Digital Moisture Meter - DMM B18

Connect
Get Data
Records
User Profile
Help
Clients

Status
24071801 is Connected

Client's records

client2 **Delete**
client3 **Delete**
client6 **Delete**

Client Details: client6

Client Name: client6
Location: location6
Total Weight: 33
Vendor ID: ssss
Remarks: Remarks 6
Truck Numbers: 453

View Data **Send File** **Send as Excel** **Send as Pdf**


Click the **“Clients”** button to view detailed client information.

To remove a client, click the **“Delete”** button next to their data.

Help Screen:

Click the **“Help”** button to access the **FAQ** and **User Guide**.

The FAQ is available in **both Hindi and English**.



Note: By default, the application is pre-filled with information for Innovative Instrument Company.

Users can update the company profile with their own details, including name, address, email, phone number, and logo, as shown above.

The end

